

*The method of software upgrade for
Tablet PC*


B988

Step 1
Let the Tablet be turned off




Step 2

Find and Click on upgrading tool "B988upgrading tool"




Step 3
Click on the "tools"



Step 4

Click on "IDT_V200 (V1.0.0.05)"



Step 5

Click on "IDT_MS1211"

IDTLog	2013/12/2 16:07
trace	2013/12/2 16:07
AdbWinApi.dll	2013/7/4 10:57
AdbWinUsbApi.dll	2013/7/4 10:57
fastboot	2013/7/4 10:57
IDT Help	2013/7/4 10:57
IDT	2013/10/21 16:40
IDT_MS1211	2013/7/4 10:57
IDT_MS1211.exe	2013/10/7 14:41
IDTCf	2013/12/3 16:11
merg	2013/7/4 10:57
Merg	2013/7/4 10:57
MFC4	2013/7/4 10:57
MFC4	2013/7/4 10:57
MFCO42D.DLL	2013/7/4 10:57
Model.dll	2013/7/4 10:57
MSVCIRTD.DLL	2013/7/4 10:57
MSVCP60.DLL	2013/7/4 10:57
MSVCP60D.DLL	2013/7/4 10:57
MSVCRTD.DLL	2013/7/4 10:57
USB Map	2013/7/4 10:57


Step 6

Click on the icon of setting as follows:




Step 7

Input three characters "1""2""3" and click on "OK"




Step 8

Click on the items in turn as follows to choose right model
dll



Step 9

Click on the items in turn as follows to choose software




Step 10

Click on the icon of starting as follows:




Step 11

Then appear a interface as follows:



Step 12

And then the interface show the words as follows:




Step 13

Press button of power and volume "+" at the same time



Step 14


Then the LCD screen show "fastboot mode:"



fastboot mode:


Step 15

Connect the tablet PC and computer with USB cabel




Step 16

This interface shows the process of upgrading software




Step 17

This interface shows the tablet had been finished upgrading successfully




Step 18

Then the tablet starts to boot its system




Step 19
Unplug the USB cabel




Step 20

When show this interface, click on the item as follows:




Step 21
And then show this interface




Step 22

Then you can click on the item in the iinterface as follows:




Step 23

Click on the item in the iinterface as follows:




Step 24

Click on the item in the iinterface as follows:




Step 25

Click on the item in the iinterface as follows:




Step 26

Click on the item in the iinterface as follows:




Step 27

Click on the item in the iinterface as follows:



Step 29

Click on the item in the iinterface as follows:



Step 30

Click on the icon of "OK" what the LCD screen shows as follows:



Step 31

This interface means you can use the tablet normally



Only for reference about the above content

Thanks for reading