

**PATROL HAWK**

**Centre Monitoring System  
PH-BC911 (Operation)**

**深圳市巡鷹安防科技有限公司**


SHENZHEN PATROL HAWK TECHNOLOGY CO.,LTD

# 1. Unzip the package of center monitoring system

The screenshot shows a file explorer window with the following content:

Item Name	Modified Date	Time	Type	Size
AlarmSystem-2.0.2	2017/11/20	17:47	文件夹	
Patrol Hawk Center Monitoring System-2.0.2.zip	2017/11/20	17:48	WinRAR ZIP 压缩...	11,890 KB
backUp	2017/7/17	9:23	文件夹	
BfVoice	2017/7/17	9:23	文件夹	
en	2017/7/17	9:23	文件夹	
en-us	2017/7/17	9:23	文件夹	
ErrorLog	2017/11/20	17:47	文件夹	
images	2017/7/17	9:23	文件夹	
msc	2017/7/17	9:23	文件夹	
upload	2017/7/17	9:23	文件夹	
zh-CHS	2017/7/17	9:23	文件夹	
Alarming.wav	2011/5/25	16:54	媒体文件 (.wav)	42 KB
<b>AlarmSystem.exe</b>	2017/11/20	17:45	应用程序	2,255 KB
BeauPhone.dll	2016/12/28	8:51	应用程序扩展	1,264 KB
Call.wav	2017/3/31	15:59	媒体文件 (.wav)	155 KB
codefile.txt	2016/3/14	10:40	文本文档	16 KB
CSkin.dll	2016/5/18	18:12	应用程序扩展	2,670 KB
icon.ico	2011/4/13	10:31	图标	10 KB
MonitoringCenter.BLL.dll	2017/7/20	10:47	应用程序扩展	29 KB
MonitoringCenter.DAL.dll	2017/11/14	10:27	应用程序扩展	101 KB
MonitoringCenter.DBUtility.dll	2017/7/20	10:47	应用程序扩展	14 KB
MonitoringCenter.Model.dll	2017/7/20	10:47	应用程序扩展	20 KB
MonitoringCenter.Receivers.dll	2017/11/14	10:27	应用程序扩展	142 KB
msc.dll	2017/3/9	16:14	应用程序扩展	4,190 KB
Newtonsoft.Json.dll	2016/6/13	23:06	应用程序扩展	473 KB

## 2. Unzip the package of center monitoring system



The image shows a 'Login' dialog box with a red padlock icon on the left. It contains two input fields: 'Admin:' and 'Password:'. Below the 'Password:' field is a blue link that says 'Forgot password'. At the bottom are two buttons: 'Confirm' and 'Cancel'. Two blue arrows point from the text labels on the right to the input fields: one from 'Account name' to the 'Admin:' field, and one from 'Enter password' to the 'Password:' field.

Account name

Enter password

Note: You have to register an account with your email address at first time login.

Alarm Monitoring System V2.0.2 — Administrator Name: maggie@phalarm.com — Current region : All

Function(F) Config(C)

Alarm Records User Location Log Records Config Increase Decrease Leave

Current region: All(7)

Alarm Records Arm Records Disarm Records User Distributed

Add User Search Export Arrearage User Will Arrearage User

User ID	User Name	MAC	Machine code	Host Name
7	Clistenes	F0FE6B50BD6C	F0FE6B50BD6C	Vcare
6	XunyingTest	ACCF23C4F4DB	ACCF23C4F4DB	Vcare
5	law	F0FE6B50C48D	F0FE6B50C48D	Vcare
4	Oscar Fractalia	ACCF23E19C7F	ACCF23E19C7F	Vcare
3	KK alarms	F0FE6B5092FD	F0FE6B5092FD	Vcare
2	Patrol Hawk alarm02	ACCF23C939D2	ACCF23C939D2	Vcare
1	Testing	F0FE6B4C0DE2	F0FE6B4C0DE2	Vcare

Heero Yuy

Online days: 63 days  
Temperature: 24.2°C  
Humidity: 58.0%  
Address: Loxley ลอดจันทน์

Status:

Control:

Detector:

Please confirm the internet has connected. Total: 7

Page: 1/1 |< < 1 > >| 1 Go

Connected

Function(F) Config(C)

Alarm Records User Location Log Records Config Increase Decrease Leave

Current region: All(7)

All(7)

1. Click "add user"

**Add User**

Detail - User

Detail

Required

User Name  Host Name

MAC  Region

Installation date

Host Address

Member Name1  Member Phone1

Option

Pay Deadline  Host Status

Host number

Member Name 2

Member Phone 3

Member Phone 2

Member Phone 5

Member Phone 4

Site map

2. Fill in the information about the alarm panel.  
Please find the MAC number on the reverse of alarm panel.

Map

3. Move the coordinate icon to an actual position for the alarm installs.

4. Confirmed above settings.

Base Operate

Add Edit Delete

Clear Cancel **Confirm**

User ID
7
6
5
4
3
2
1

Alarm Records Arm Records Disarm Records User Distributed

Add User Search Export Arrearage User Will Arrearage User

User ID	User Name	MAC	Machine code	Host Name	Region	Host Address	Host Status	Installation date
7	Clistenes	F0FE6B50BD6C	F0FE6B50BD6C	Vcare	All	Avenida Italia, 728	Offline	9/14/2017 5:03
6	XunyingTest	ACCF23C4F4DB	ACCF23C4F4DB	Vcare	All	Xunying	Offline	9/5/2017 12:01
5	law	F0FE6B50C48D	F0FE6B50C48D	Vcare	All	thailand	Disarm	9/4/2017 11:16
4	Oscar Fractalia	ACCF23E19C7F	ACCF23E19C7F	Vcare	Madrid	Madrid	Offline	8/25/2017 3:22
3	KK alarms	F0FE6B5092FD	F0FE6B5092FD	Vcare	India	India	Offline	8/1/2017 6:06 P
2	Patrol Hawk alarm02	ACCF23C939D2	ACCF23C939D2	Vcare	India	Shenzhen,China	Offline	7/31/2017 5:04
1	Testing	F0FE6B4C0DE2	F0FE6B4C0DE2	Vcare	All	Shenzhen, China	Offline	7/31/2017 3:07



Control the alarm panel remotely through PC, such as arm/disarm/home stay arm etc.



Click the sensor to check the working status, such as door open/close status online/off status, low battery status


Heero Yuy
→ Online Status


Online days: 63 days  
 Temperature: 24.1°C  
 Humidity: 54.4%  
 Address: Loxley ลอยขย


Disarm status


Status:   


Control:   

Detector:


  
Door


  
Motion

  
Smoke

  
Gas

  
Emergency

  
Medical



1. Please arm the alarm panel on mobile phone app or through monitoring system
2. Triggered alarm detectors or panic button to activate alarm.
3. The alarm push notification will be sent to mobile phone app and alarm monitoring system as well.



User Name:law  
Information:Emergency alarm(Emergency alarm 01)  
Alarm time:11/21/2017 3:40:18 PM MAC:F0FE6B50C48D  
Host Address:thailand

From alarm push notification, the staff in center monitoring station can get the details of current alarming alarm device, user name, alarm types, alarm date and time, MAC address and installation address

The image shows a mobile application interface for a user named 'Heero Yuy'. At the top, there is a house icon and the name 'Heero Yuy'. Below this, several status metrics are listed: 'Online days: 63 days', 'Temperature: 23.8°C', 'Humidity: 53.7%', and 'Address: Loxley ๓๓๓๓๓๓๓๓'. A 'Status:' section contains several icons: a padlock (locked), a bell (alarm), a Wi-Fi signal, a signal strength indicator, a battery level, and a person icon. A red box highlights the 'Control:' section, which shows a padlock icon and the text 'Successful'. Below this, a 'Detector:' section lists various sensors with icons: 'Door' (door icon), 'Motion' (person icon), 'Smoke' (flame icon), 'Gas' (flame icon), 'Emergency' (SOS icon), and 'Medical' (ambulance icon).

Call police or inform the relevant departments to deal with the alarm.

Alarm Monitoring System V2.0.2 — Administrator Name: maggie@phalarm.com — Current region : All

Function(F) Config(C)

Alarm Records User Location Log Records Config Increase Decrease Leave


Current region: All(7)

All(7)  
India(2)  
Madrid(1)

Alarm Records Arm Records Disarm Records User Distributed

Deal All Search Export  Fire alarm  Water leakage alarm  Medical call alarm  SOS emergency alarm  Door/window sensor alarm

Alarm ID	Alarm time	Disarm time	Installation date	MAC	User Name	Disarm status	Host Address	Information
3	11/21/2017 3:40 PM		9/4/2017 11:16 AM	F0FE6B50C48D	law	Alarm have not been processed	thailand	Emergency alarm(Emergency alarm
2	11/21/2017 3:40 PM		9/4/2017 11:16 AM	F0FE6B50C48D	law	Alarm have not been processed	thailand	Emergency alarm(Emergency alarm
1	11/21/2017 3:40 PM		9/4/2017 11:16 AM	F0FE6B50C48D	law	Alarm have not been processed	thailand	Emergency alarm(Emergency alarm



User Name:law  
Information:Emergency alarm(Emergency alarm 01)  
Alarm time:11/21/2017 3:40:18 PM MAC:F0FE6B50C48D  
Host Address:thailand



Alarm Monitoring System V2.0.2 — Administrator Name: maggie@phalarm.com — Current region : All

Function(F) Config(C)

Alarm Records User Location Log Records Config Increase

Current region: All (7)

All (7)

Deal All Search Export

Alarm ID	Alarm time	D	ti
3	11/21/2017 3:40 PM		
2	11/21/2017 3:40 PM		
	11/21/2017 3:40 PM		

**Deal Alarm**

Remark

1. Click " Deal All " or deal the alarm one by one.
2. Click "Deal Alarm" .

Cancel Deal Alarm



**User Name:law**  
**Information:Emergency alarm(Emergency alarm 01)**  
**Alarm time:11/21/2017 3:40:18 PM MAC:F0FE6B50C48D**  
**Host Address:thailand**

Total:3

Page:1/1 |< < 1 > >| 1 Go

Check all the installed alarm system in different places.

Administrator Name: maggie@phalarm.com — Current region : All

Records Config Increase Decrease Leave

Alarm Records Arm Records Disarm Records User **Distributed**

Total 7 Refresh

地图 卫星图像

酒泉市 张掖市 金昌市 武威市 兰州市 定西市 平凉市 庆阳市 天水市 宝鸡市 西安市 渭南市 咸阳市 延安市 榆林市 鄂尔多斯市 银川市 石嘴山市 乌鲁木齐市

海西蒙古族  
藏族自治州  
海南藏族自治州  
青海  
宁夏回族自治区  
临夏回族自治州  
甘肃  
甘南藏族自治州  
果洛藏族自治州  
玉树藏族自治州  
阿坝藏族  
羌族自治州  
四川

中国

Heero Yuy

Online days: 63 days  
Temperature: 23.5°C  
Humidity: 50.3%  
Address: Loxley 100031000

Status:

Control:

Detector:   
Door Motion  
   
Smoke Gas  
   
Emergency Medical  
   
W-leakage More

激活 Windows  
转到“设置”以激活 Windows。

## Multi-level account management settings

Function(F) Config(C)

Alarm Records User Location Log Records Config Increase Decrease Leave

Current region: All(7)

Alarm Records Arm Records Disarm Records User Distributed

Deal All Search Export  Fire alarm  Water leakage alarm  Medical call alarm  SOS emergency alarm  Door/window sensor alarm

Alarm ID	Alarm time	Disarm time	Installation date	MAC	User Name	Disarm status	Host Address	Information
							cessed thailand	Emergency ala
							cessed thailand	Emergency ala
							cessed thailand	Emergency ala

**System Config**

Config Administrator DataBase Region Region administrator Alarm sound management

Administrator Name	Instruction
LES	
LawEnforce	

Admins

Administrator Name:

Password:

Confirm Password:

Instruction:

Add Delete **Confirm**

**Operation Permissions**

- Add Administrator
- Edit Administrator
- Delete Administrator
- Deal Alarm
- Delete Alarm Records
- Delete Log Records
- Add User
- Edit User
- Delete User
- Add System Config
- Edit System Config
- Delete System Config
- Start System
- Stop System
- Exit System
- Add Order
- Edit Order
- Delete Order

All

**View Permissions**

- Administrator Record
- Alarm Records
- User Record
- Log Records
- System Config Record
- Map
- Database Information
- Order info

All

For more information, please feel  
free to contact us.

[Maggie@phalarm.com](mailto:Maggie@phalarm.com)